Casing In Your Book Block

Make sure you read these directions carefully before beginning

Place the book block between backing boards, a securing vice, or just between your knees. Using your glue brush, liberally



apply Jade to the spine of the block. Take your Supercloth and glue the center along the spine. Burnish with bonefolder. your Cover the supercloth with a strip of provided Kraft paper; burnish again.

4 Center the other strip of Kraft paper btwn. the boards.





Now it's time to trim the of corners your material. Gauging how much to trim can be tricky - but a proper amount to leave extending beyond the

corner of the boards is just over the thickness of the boards. Cut at a 45° angle.

8 Now it's time to place the book block into the cover.

Holding the book inside of its jacket - knock it back against a hard surface to make sure it's fully in place.



9 Once your block is in place (make sure there is an even extension on the

top and bottom) take a sheet of your scrap paper and place it behind the first page in your diary block. Now take your brush and apply a coating of Jade across the whole end page.



TIP: Make sure to completely cover Supercloth as this will act as the chief means of support between the block & case.

Shut the cover, and apply pressure.

Now very carefully, hold the book & case in place and flip.


Repeat the same gluing process on this side.

2 Place your cover material face down on a sheet of scrap paper or newprint. Glue the entire back side of your cover material - make sure not to miss the edges & corners.


TIP: Always start from the center & work out to avoid rips, folds, or creases to your material. Work quickly as Jade dries fast. If you'd like to slow down the drying time - try adding wheat paste or methyl cellulose to your Jade for added drying time

3 Cut a "center guide" out of scrap - it should be at least 4mm more then the width of the spine (to compensate for the board depth).

Eye or generally gauge the center of the material & place your "center guide." Now, butt your center boards up to the center guide making sure the top & bottom margins are the same size. Once the boards are down, remove the center guide.



6 Long sides always get folded first. Take your bonefolder and tease the material up - burnishing flat along the edge of the Continue flattening the material to the inside of the boards. Pinch in the corners with your fingernail.



drying out - don't be afraid to reapply in specific areas.

Just be careful to not add to much as to avoid pooling when burnished.

Leave to dry under weight for several hours, or as long as you'd like. This will help ensure that your boards do not buckle or curl.

10 Leave your book to dry under weight - preferably overnight to help ensure flatness and to prevent your boards from curling.

Congratulations you have finished completing your diary!

From everyone at Talas, have a happy and a healthy year!





talasonline.com