

## Vellum Mounting

### MATERIALS

*Vellum ~ size of board + 40mm all around*

*Board ~ 12mm Plywood*

*Glue ~ starch paste*

*Lining Paper ~ standard (acid-free)*


1. Line the upper surface of your board with lining paper - usually white or light cream, as it will affect the color of the Vellum- use Acid-Free paper for longevity.

2. Dampen Vellum on both sides with a wet sponge.

3. Leave until water has sunk into the Vellum.

4. Place the vellum face down on the table.

5. Place the Board face down on top of the vellum.



6. Cut the corners of the vellum so that, when wrapped, they will fit properly around the Plywood, overlapping on the reverse, but not on the edges.

7. Paste outer 30mm of the vellum, and the outer 30mm of the board. There will be a thin strip of un-pasted skin near the front edges, to ensure that the glue does not creep under the front surface of the vellum.

8. Pull the vellum around the edge of the board, and press down on the reverse of the board one side at a time, then one end at a time, push out air as you progress, re-wet edges of vellum if it seems reluctant to stretch tightly around the edges of the board.

*If the vellum does not stay down, use pins, staples or tape to hold it.*

9. Cover reverse of the board with more glued lining paper, removing pins or tape as you go.

10. Wipe the vellum face with a wet cloth to remove grit and marks.

11. Leave to Dry. As skin dries it will become taught around the board.